

TAB A93 firmware update tutorial

Warning ! Ensure your device is fully charged before attempting to upgrade. Remember to back up any important information prior to the performing the upgrade. Remove microSD card. Installing the wrong firmware or not following installation instructions may cause damage of your device. Firmware update software can be used on Windows system only. We do not recommend using eSATA/USB or USB 3.0 ports to perform this upgrade.

1) Make sure to check the serial number of your device to download proper firmware.


! Using the firmware designed for device with a different serial number may damage your device.!

Go to **Support** -> **Download center** on our website – www.goclever.com or check **Support** tab on TAB A93 site. Next download software to run on your computer from link below


http://download.goclever.net/serwis/tab/LiveSuitPack_1.05.zip

2) Unpack **GCA93*.zip** and **LiveSuitPack_1.05.zip**. Next in **LiveSuitPack_1.05** folder run **LiveSuitPack.exe** and wait (software will unpack necessary files)


3) Run **LiveSuit.exe** located in **LiveSuitPack_1.05** folder next click on **SelectImg**



4) Select **GCA93*.img** file




5) Software window should look like below, do not close **LiveSuit** application




6) **Turn off your tablet.** Press and hold **Back** button next connect to **microUSB cable**. When computer find new hardware release button. Windows will ask you for the driver for your device – please point **UsbDriver** folder located in **LiveSuitPack_1.05** folder

TIP: You can verify if the driver has been installed correctly by clicking on your Windows device manager. A properly installed driver should look like below




7) Window will appear – select **YES**




TIP: If you do not see the picture above, please disconnect USB cable form tablet and connect again.


8) Click **YES** in next window as well



9) Update process will start



10) After a successful update message will appear. Select **OK**.



11) After update finish. Close **LiveSuit** app using **Exit** button. Now you can disconnect USB cable from tablet. Press **Reset** in tablet. Turn on tablet and after Android system start wait 5 minutes.

TIP: If tablet start automatically after reset. Don't turn off tablet, wait until system Android loads and wait 5 minutes.

12) You have successfully upgraded your TAB A93.